

Advanced scripting with ObsInp

(Erstmal intern, bis alles ausgiebig getestet ist)

Mixing scripts of different type

Sometimes, it is desired to mix different types of measurement in a single script, e.g., pointings and position switches. In the normal case, ObsInp will interpret a script as of such a type, as the input tab which was used, e.g., if one would call a pointing script from the FSwitch tab, ObsInp would load the source as FSwitch.

To avoid this behavior, one can simply add the Form keyword to the script, followed by the name of the input mask

```
3C123 ; Catalog Default ; CoordinateSystem Equatorial ; Equinox B1950 ;
Help Defaults ; ObjectLatitude 29 34 14.0 " ; ObjectLongitude 04 33 55.2 s ;
POINTcorr 1 ; SCANDirection Longitude/Latitude ; SCANLength -4 ; SCANRepeats
2 ;
SCANRotation 0.0 ; SCANTime 30 ; Scanning_in Azimuth/Elevation ; ZigZag
True; Form Pointing
```

(a pointing on 3C123)

```
3C48 ; Amplitude 0 ; Catalog Default ; CoordinateSystem Equatorial ;
CosDrv No ; Equinox B1950 ; FreqThrowHi -4.0 ; FreqThrowLo 0 ; Help Defaults
;
LatOff 0.0 ; LonOff -1d ; NRepeats 1 ; ObjectLatitude 52 26 13 " ;
ObjectLongitude 14 09 33.5 s ;
Offset_in CoordinateSystem ; SCANRepeats 1 ; SCANTime 120 ; SourceVelocity
0.0 ;
StartPosAng 180 ; TrackParAng On ; VMode Fixed ; VelSystem VLRS; Form
FSwitch
```

(an fswitch on 3C48)

Lets assume these scripts were saved in the files poitest and fswtest. Then one can call both from the same Script

```
@poitest
@fswtest
```

Of course one can also set the receiver, frequencies and use different sources

```
FE: S110mm; VERn 1; Frequency 2.6
@poitest:3C295
@fswtest:3C295
FE: S110mm; VERn 1; Frequency 2.5
@poitest:3C295
```

@fswtest:3C295

Set focus/pointing offsets from a script

Using the Form keyword, one has also access to pointing and focus offsets.

```
3C48 ; Catalog Default; NULE 10; SetAbsolut Yes; Form PointingCorrection
```

Use SetAbsolut Yes or SetAbsolut No to set the value of the associated Combobox.

```
3C48 ; Catalog Default; ZLinear -10; QPosition 1; Form Focus_Offsets
```

QPosition 1 means, the focus offset will be put at the top of the queue, while QPosition 0 puts it to the current position (the latter being more useful in a script). Note, that one has to use a (dummy) source and catalog in the script.

Recursive use of source names

A feature often used is to apply scripts to different sources. Although each script contains a source and catalog name (at least when created with ObsInp), one can call the script with a different source name, e.g. @poitest:3C48. It is even possible to recursively use this feature. Assume you want to use the script

```
FE: S110mm; VERn 1; Frequency 2.6  
@poitest:3C295  
@fswtest:3C295  
FE: S110mm; VERn 1; Frequency 2.5  
@poitest:3C295  
@fswtest:3C295
```

(lets call it masterscript) on many sources. Then you just have to remove all source names from the script

```
FE: S110mm; VERn 1; Frequency 2.6  
@poitest  
@fswtest  
FE: S110mm; VERn 1; Frequency 2.5  
@poitest  
@fswtest
```

Now one can call @masterscript:W3MAIN from any form, and it will correctly replace the sources. If it is called without source name, ObsInp will use the sources it finds in the root scripts (it doesn't work, if the masterscript still contains source names).

From:
<https://eff100mwiki.mpifr-bonn.mpg.de/> - **Effelsberg 100m Teleskop**

Permanent link:
https://eff100mwiki.mpifr-bonn.mpg.de/doku.php?id=information_for_astronomers:user_guide:advancedscripting&rev=1343740754

Last update: **2014/08/05 15:20**

